


External Light Source- Transmission Reflection


-TRACmd.pyc

Author: Wei-Kai Lee




Objective

- This program calculates the total transmittance and the reflectance.



T, R of a coherent set


TMM + Coherent stacking



External Light Source

Finite State Machine Method


(a) Isotropic Case/ Uniaxial and $\hat{c} // \hat{z}$ case



$$L_i^+ = T_i^+ L_{i-1}^+ + R_i^- L_i^-$$

$$L_i^- = T_{i+1}^- L_{i+1}^- + R_{i+1}^+ L_i^+$$

(b) General Case



$$L_i^1 = T_i^{11} L_{i-1}^1 + T_i^{12} L_{i-1}^2 + R_i^{13} L_i^3 + R_i^{14} L_i^4$$

$$L_i^2 = T_i^{21} L_{i-1}^1 + T_i^{22} L_{i-1}^2 + R_i^{23} L_i^3 + R_i^{24} L_i^4$$

$$L_i^3 = T_{i+1}^{33} L_{i+1}^3 + T_{i+1}^{34} L_{i+1}^4 + R_{i+1}^{31} L_i^1 + R_{i+1}^{32} L_i^2$$

$$L_i^4 = T_{i+1}^{43} L_{i+1}^3 + T_{i+1}^{44} L_{i+1}^4 + R_{i+1}^{41} L_i^1 + R_{i+1}^{42} L_i^2$$

How to execute TR calculator

python: windows
python3: mac, linux

```
>python TRACmd.py
```

Execution file

```
>>> Please insert username : user-1  
Now reading nk file ( \ \ \sim\ma
```

Type user name

```
TRA Setting is not built in ../../SETTING/user-1  
Now saving the default TRA setting.  
<TRACmd>
```

<< LegendDesign > SETTING > user-1

| 名称 | 修改日期 |
|------------------|-----------|
| log | 2020/4/12 |
| materialMgr.mMgr | 2020/4/12 |
| rtauCmd.setting | 2020/4/12 |
| TRACmd.setting | 2020/4/12 |

Help

```
non-saving the default run setting.  
<TRACmd> ?  
User Control Command  
=====
```

1. Setting Command:

| | |
|------------|------|
| changeUser | exit |
|------------|------|

Material Manager Command
=====

1. Setting Command:

| | |
|----------|---------|
| printMgr | saveMgr |
|----------|---------|

Structure/Structure List Command
=====

1. Structure List Command:

| | |
|--------------------|--------------------|
| ReadStructListPath | ReadStructListName |
| SaveStructListPath | SaveStructListName |
| readStructList | saveStructList |

2. Structure Command:

| | |
|----------------|----------------|
| ReadStructPath | ReadStructName |
| SaveFilePath | SaveFileName |
| readStruct | deleteStruct |

3. Print Information Command:

| | |
|-----------------|------------------------|
| printStructInfo | printStructSettingInfo |
| printListInfo | |

4. Result Command:

| | |
|----------------|----------------|
| ResultFilePath | ResultFileName |
|----------------|----------------|

deleteResult
save_run_time_result_Bool
resetSN

Help

Transmission/Reflection Command

1. Setting Command:

| | |
|-------------------|-----------------|
| SettingFilePath | SettingFileName |
| setDefaultSetting | printTRAInfo |
| loadTRASETting | saveTRASETting |

2. kxky:

| kxko | kyko | Wavelength | ----Parameter |
|------------------------|-----------------|------------|---------------|
| IncidenceWaveDirection | ---- | Parameter | |
| runTRA_kxky | readResultskxky | | |
| plotTRAvsWV_kxky | plotTRAvsKxky | | |
| plotTRAContourkxky | writeKxkyMatrix | | |

3. angle:

| Theta | Phi | Wavelength | ----Parameter |
|------------------------|------------------|------------|---------------|
| IncidenceWaveDirection | ---- | Parameter | |
| runTRA_Angle | readResultsAngle | | |
| plotTRAvsWV_Angle | plotTRAvsAngle | | |
| plotTRAContourAngle | writeAngleMatrix | | |

4. Plot Bool:

changeFigshowBool


5. Run Time Bool:

| | |
|----------------------|-----------------------|
| runtime_write_matrix | runtime_plotvsWV |
| runtime_plotvsKY | runtime_plotvsContour |



Calculating Workflow

Choose one method to load structure(s)




Default Setting

Print setting

```
>>> printTRAInfo
```

```
Setting file path : ../../SETTING/user-1
Setting file name : TRACmd.setting
Wavelength (nm) : 380.00000:10.00000:780.00000
Theta (degree) : 0.00000:1.00000:90.00000
Phi (degree) : 0.0
kx/ko : 0.00000:0.10000:1.00000
ky/ko : 0.00000:0.10000:1.00000
Incidence Direction : TOP
Save-run-time result bool : True
Run-time-write-matrix bool : False
Run-time-plot-TRA-contour bool : False
Run-time-plot-TRA-vs-Wavelength bool : False
Run-time-plot-TRA-vs-Angle or -kxky bool : False
Figure Show Bool : True
```



| 名稱 | 修改日期 |
|------------------|-----------|
| log | 2020/4/12 |
| materialMgr.mMgr | 2020/4/12 |
| rtacmd.setting | 2020/4/12 |
| TRACmd.setting | 2020/4/12 |

All the setting would **automatically** saved into the setting file when the program **finished**. The user can set the setting at first or share the setting files with others.

Setting

```
Wavelength (nm) : 380.00000:10.00000:780.00000
```

The wavelength of the incident light. The format of the wavelength is the same as in the parameter scan. (i.e. value/start:space:end/(value1,value2,value3))

Wavelength setting method

```
<TRACmd> help Wavelength  
Set wavelength (nm). (Empty for delete setting)  
[Usage] Wavelength [wavelength] - single value, start:spacing:end, (v1,v2,v3,v4)
```

Setting

```
Theta (degree) : 0.00000:1.00000:90.00000  
Phi (degree) : 0.0
```

The angle of the incident wave.

Angle setting method

```
<TRACmd> help Theta  
Set theta (degree). (Empty for delete setting)  
[Usage] Theta [theta] - single value, start:spacing:end, (v1,v2,v3,v4)  
  
<TRACmd> help Phi  
Set phi (degree). (Empty for delete setting)  
[Usage] Phi [phi] - single value, start:spacing:end, (v1,v2,v3,v4)
```

```
kx/ko : 0.00000:0.10000:1.00000  
ky/ko : 0.00000:0.10000:1.00000
```

The tangential components of the incident wave.

kx/ko and ky/ko setting method

```
<TRACmd> help kxko  
Set kx/ko. (Empty for delete setting)  
[Usage] kxko [kxko] - single value, start:spacing:end, (v1,v2,v3,v4)  
  
<TRACmd> help kyko  
Set ky/ko. (Empty for delete setting)  
[Usage] kyko [kyko] - single value, start:spacing:end, (v1,v2,v3,v4)
```

Only one would be used in a calculation.



Run Time Setting

```
Save-run-time result bool : True
```

Whether to save the data in the memory after the calculation. If the user would like to execute plot or other data manipulation commands, the save-run-time-result bool should be “True”. However, the user should notice the memory usage when scanning a lot of parameters.

```
Run-time-write-matrix bool : False
```

Whether to save the matrix format when calculation.

```
Run-time-plot-TRA-vs-Wavelength bool : False  
Run-time-plot-TRA-vs-Angle or -kxky bool : False
```

Whether to plot the TRA results when calculation.

Calculate TRA

| MATERIAL | | THICKNESS (nm) |
|------------------------------------|-----|----------------|
| | 1.0 | X |
| | 1.5 | X |
| wavelength (nm) : 480.0:10.0:600.0 | | |

Calculate TRA

Structure file (DBR)

| MATERIAL | THICKNESS (nm) |
|----------|----------------|
| air | X |
| 1.5 | 100 |
| 2.5 | 60 |
| 1.5 | 100 |
| 2.5 | 60 |
| 1.5 | 100 |
| 2.5 | 60 |
| air | X |

wavelength (nm) : 480.0:10.0:600.0

| Name | readfilename | readfilepath | savefilename |
|-------|--------------|--|--------------|
| #sds1 | sfile-1.txt | ./Example/structure/DielectricStacking | sfile-1 |
| #sds2 | sfile-2.txt | ./Example/structure/DielectricStacking | sfile-1 |



Calculate TRA

Structure file (transparent device-1)

| MATERIAL | THICKNESS (nm) | |
|----------|----------------|------|
| air | X | |
| Al | 10:5:20 | scan |
| LiF | 1.000000 | |
| B3PYMPM | 50 | |
| CBP | 20.000000 | |
| TAPC | 20 | |
| cito | 50 | |
| glass | X | |

wavelength (nm) : 450:10:650.0

EML :

| | |
|---------------|------------------|
| Layer no | : 5 |
| Position (nm) | : 10.000000 |
| ratio | : 1.000000 |
| QY | : 1.000000 |
| Fluorescence | : cbp_irppy2acac |
| DOF | : cbp_irppy2acac |

Calculate TRA

Structure file (transparent device-2)

| MATERIAL | | | THICKNESS (nm) | |
|----------|---------|--|----------------|------|
| | air | | | X |
| | Al | | 10:5:20 | scan |
| | LiF | | 1.000000 | |
| | B3PYMPM | | 50 | |
| | CBP | | 20.000000 | |
| | TAPC | | 20 | |
| | cito | | 50 | |
| | glass | | | X |
| | air | | | X |

wavelength (nm) : 450:10:650.0

EML :

| | | |
|---------------|---|----------------|
| Layerno | : | 5 |
| Position (nm) | : | 10.000000 |
| ratio | : | 1.000000 |
| QY | : | 1.000000 |
| Fluorescence | : | cbp_irppy2acac |
| DOF | : | cbp_irppy2acac |

Example-1.txt sfile-1-air.txt structureList-TRA.Cmd.txt

| Name | readfilename | readfilepath | savefilename | |
|------|-----------------|---------------------------------|--------------|-----|
| #Ts1 | sfile-1.txt | ./Example/structure/Transparent | sfile-1 | ../ |
| #Ts2 | sfile-1-air.txt | ./Example/structure/Transparent | sfile-1 | ../ |

Calculate TRA

```
>>> ReadStructListPath ./Example/structure/DielectricStacking
>>> ReadStructListName structureList-TRACmd.txt
>>> readStructList

Now reading structure list file ./Example/structure/DielectricStacking\structureList-TRACmd.txt


| No./Name | filename    | savefilename | CommandID | Check | readfilepath                                                          |
|----------|-------------|--------------|-----------|-------|-----------------------------------------------------------------------|
| #sds1    | sfile-1.txt | sfile-1      | 0.0       | X     | ./Example/structure/DielectricStacking ../../Example/TRACmd/Dielectri |
| #sds2    | sfile-2.txt | sfile-1      | 0.0       | X     | ./Example/structure/DielectricStacking ../../Example/TRACmd/Dielectri |


Structure file reading...
Now reading structure file ./Example/structure/DielectricStacking\sfile-1.txt
Now reading structure file ./Example/structure/DielectricStacking\sfile-2.txt
```

```
>>> ReadStructListPath ./Example/structure/Transparent
>>> ReadStructListName structureList-TRACmd.txt
>>> readStructList

Now reading structure list file ./Example/structure/Transparent\structureList-TRACmd.txt


| No./Name | filename        | savefilename | CommandID | Check | readfilepath                                                |
|----------|-----------------|--------------|-----------|-------|-------------------------------------------------------------|
| #Ts1     | sfile-1.txt     | sfile-1      | 0.0       | X     | ./Example/structure/Transparent ../../Example/TRACmd/Tr     |
| #Ts2     | sfile-1-air.txt | sfile-1      | 0.0       | X     | ./Example/structure/Transparent ../../Example/TRACmd/Transp |


Structure file reading...
Now reading structure file ./Example/structure/Transparent\sfile-1.txt
Now reading structure file ./Example/structure/Transparent\sfile-1-air.txt
```

Calculate TRA

```
>>> printStructInfo
```

```
*****
```

```
Name: #sds1
```

```
[#] Material Thickness(nm)
```

```
-----
```

```
[1] 1.0 X
```

```
[2] 1.5 X
```

```
wavelength(nm) : 480.00000:10.00000:600.00000
```

```
Device number : 1
```

```
*****
```

```
Name: #sds2
```

```
[#] Material Thickness(nm)
```

```
-----
```

```
[1] air X
```

```
[2] 1.5 100.0
```

```
[3] 2.5 60.0
```

```
[4] 1.5 100.0
```

```
[5] 2.5 60.0
```

```
[6] 1.5 100.0
```

```
[7] 2.5 60.0
```

```
[8] air X
```

```
wavelength(nm) : 480.00000:10.00000:600.00000
```

```
Device number : 1
```

```
*****
```

```
Name: #Ts1
```

```
[#] Material Thickness(nm)
```

```
-----
```

```
[1] air X
```

```
[2] Al 10.00000:5.00000:20.00000
```

```
[3] LiF 1.0
```

```
[4] B3PYWPM 50.0
```

```
[5] CBP 20.0
```

```
[6] TAPC 20.0
```

```
[7] cito 50.0
```

```
[8] glass X
```

```
wavelength(nm) : 450.00000:10.00000:650.00000
```

```
EML Fluorescence DOF Position(nm) PLQY Ratio
```

```
-----
```

```
[5] cbp_irppy2acac cbp_irppy2acac 10.0 1.0 1.0
```

```
Device number : 3
```

```
*****
```

```
Name: #Ts2
```

```
[#] Material Thickness(nm)
```

```
-----
```

```
[1] air X
```

```
[2] Al 10.00000:5.00000:20.00000
```

```
[3] LiF 1.0
```

```
[4] B3PYWPM 50.0
```

```
[5] CBP 20.0
```

```
[6] TAPC 20.0
```

```
[7] cito 50.0
```

```
[8] glass X
```

```
[9] air X
```

```
wavelength(nm) : 450.00000:10.00000:650.00000
```

```
EML Fluorescence DOF Position(nm) PLQY Ratio
```

```
-----
```

```
[5] cbp_irppy2acac cbp_irppy2acac 10.0 1.0 1.0
```

```
Device number : 3
```




Calculate TRA

[illegible]

Plot

| | MATERIAL | THICKNESS (nm) |
|--|----------|----------------|
| | 1.0 | X |
| | 1.5 | X |




Calculate TRA

[illegible]

Plot

| MATERIAL | THICKNESS (nm) |
|----------|----------------|
| 1.0 | X |
| 1.5 | X |




Calculate TRA

[illegible]

Plot

| | MATERIAL | THICKNESS (nm) |
|--|----------|----------------|
| | 1.0 | X |
| | 1.5 | X |



Exit the material manager system

Exit the material manager system.

*** The material manager system would be automatically saved into the user's setting directory.

```
>>> exit
```

```
-----  
End running GOODLAB anisotropic simulator ver1.0 Sun Apr 12 21:25:18 2020  
Elapsed time : 0 day(s)/ 0 hr(s)/ 3 min(s)/ 38.60393166542053 sec(s)  
-----
```

