


Internal Light Source- Field Distribution


-DeviceFieldCmd.pyc

Author: Wei-Kai Lee




Objective

- This function is to calculate the ensemble average of the field distribution along z-axis.




Organic Light Emitting Diodes (OLEDs)



Under forward bias


- Charge injection
- Charge transport
- Exciton formation
- Light emission






The advantage of OLEDs

- R,G,B available
- High brightness, low voltage, high efficiency
- Fast response, wide viewing angle
- High Contrast
- Lightweight
- Display, lighting, other applications


Uniaxial Refraction Index



Uniaxial refractive index



Outcoupling Issue




Rigorous EM wave model

$$\eta_{EQE} = \gamma \times \eta_{exc.} \times \eta_{out}(\Theta, \Gamma) = \eta_{int.} \times \eta_{out}(\Theta, \Gamma)$$

- Due to index mismatches of OLED layers, out-coupling efficiency is **20%~30%** for a typical bottom-emitting OLED.
- Nearly **100%** internal quantum efficiency nowadays.
- Making use of **not out-coupled internal radiation** is a current issue.

Power Density/Power Dissipation




Optics in OLED


- Transition Dipole Moment (TDM)
↔ Classical Electromagnetic Oscillating Dipole

$$\mathbf{d}(\omega) = \langle \Psi_e | q\mathbf{r} | \Psi_g \rangle \langle \Phi_e | \Phi_g \rangle$$

$$R_t = \frac{\pi}{\hbar^2} \rho(\omega) |\mathbf{d}(\omega) \cdot \mathbf{E}(\mathbf{k})|^2$$



- Classical Radiation Pattern in Homogeneous Material



- 1, Special Relativity
2. Ampere's Right Hand Rule
→ Hertzian Dipole

$$I_{Hertzian}(\Omega) = \frac{3}{8\pi} \sin^2 \theta$$

Solve Procedure-1



$$\bar{\bar{G}}_{ee}^p(k_x, k_y, z, \omega) = \sum_{m=1}^4 |\hat{v}_m\rangle \langle p_m(z)|$$

Transfer
Matrix

**Homogeneous
Solution (dGF)**

Eigen-
States

**Particular
Solution (dGF)**

$$\bar{\bar{G}}_{ee}^h(k_x, k_y, z, \omega) = \sum_{m=1}^4 |\hat{v}_m\rangle \langle h_m(z)|$$

From k domain to the
 k_x - k_y - z domain

$$\bar{\bar{G}}_{ee}^p(k_x, k_y, z, \omega) = \sum_{m=1}^4 |\hat{v}_m\rangle \langle p_m(z)|$$

$$\bar{\bar{G}}_{ee}^p(k_x, k_y, z, \omega) = \sum_{m=1}^4 |\hat{v}_m\rangle \langle p_m(z)|$$

**Total Solution
(dGF)**

**Total Solution
(E, H)**

$$\bar{\bar{G}}_{ee}^t(k_x, k_y, z, \omega) = \sum_{m=1}^4 |\hat{v}_m\rangle \langle t_m(z)|$$

$$|\Phi^h(0)\rangle = \bar{\bar{M}}^a (|\Phi^h(0)\rangle + |\Phi^p(0)\rangle)$$



Dipole Orientation Distribution

對於一般的有機發光體來說，不同分子的發光偶極矩的振盪方向可能並不相同，為了要能模擬這種現象，在此我們引入了dipole orientation distribution function來模擬這種情形。


$$\langle P_z(k_x, k_y, z, \omega) \rangle = \langle \mathbf{J}(k_x, k_y, z, \omega; \alpha) | \bar{\bar{P}}_z(k_x, k_y, z, \omega) | \mathbf{J}(k_x, k_y, z, \omega; \alpha) \rangle$$

α : random variables about emitting dipoles
e.x. orientation, phase

$$\langle P_z \rangle = \sum_{i,j=x,y,z} \bar{\bar{P}}_{z,ij} \langle J_i^*(\alpha) J_j(\alpha) \rangle$$



Dipole Orientation Distribution



$$\begin{bmatrix} J_x \\ J_y \\ J_z \end{bmatrix} = -i\omega d \begin{bmatrix} e^{i\alpha_x} \sin \theta \cos \phi \\ e^{i\alpha_y} \sin \theta \sin \phi \\ e^{i\alpha_z} \cos \theta \end{bmatrix}$$

$$\langle J^2 \rangle = \langle J^* J \rangle \equiv \langle J_x^* J_x + J_y^* J_y + J_z^* J_z \rangle = \langle \omega^2 d^2 \rangle$$

Dipole Orientation Factor


$$\eta_1 = \langle \frac{1}{2}(1 - \cos^2 \theta) \rangle = \langle \frac{1}{2} \sin^2 \theta \rangle$$

$$\eta_2 = \langle \frac{1}{2} \sin^2 \theta (\cos^2 \phi - \sin^2 \phi) \rangle$$

$$\eta_3 = \langle \sin^2 \theta \cos \phi \sin \phi \rangle$$

$$\eta_4 = \langle \cos \theta \sin \theta \cos \phi \rangle$$

$$\eta_5 = \langle \cos \theta \sin \theta \sin \phi \rangle$$



$$\langle J_x^* J_x \rangle = (\eta_1 + \eta_2) \langle J^2 \rangle$$

$$\langle J_y^* J_y \rangle = (\eta_1 - \eta_2) \langle J^2 \rangle$$

$$\langle J_z^* J_z \rangle = (1 - 2\eta_1) \langle J^2 \rangle$$

$$\langle J_x^* J_y \rangle = \eta_3 \langle e^{i(\alpha_y - \alpha_x)} \rangle \langle J^2 \rangle$$

$$\langle J_x^* J_z \rangle = \eta_4 \langle e^{i(\alpha_z - \alpha_x)} \rangle \langle J^2 \rangle$$

$$\langle J_y^* J_z \rangle = \eta_5 \langle e^{i(\alpha_z - \alpha_y)} \rangle \langle J^2 \rangle$$

How to execute the calculator

python: windows
python3: mac, linux

```
>python DeviceFeildCmd.pyc
```

Execution file

```
>>> Please insert username : user-1
```

Type user name

```
TRA Setting is not built in ../../SETTING/user-1  
Now saving the default TRA setting.
```

名稱	修改
log	2020
materialMgr.mMgr	2020
rtauCmd.setting	2020
TRACmd.setting	2020



Help

```
>>> ?

User Control Command
=====
1. Setting Command:
changeUser          exit

Material Manager Command
=====
1. Setting Command:
printMgr            saveMgr

Structure/Structure List Command
=====
1. Structure List Command:
ReadStructListPath  ReadStructListName
SaveStructListPath  SaveStructListName
readStructList      saveStructList

2. Structure Command:
ReadStructPath      ReadStructName
SaveFilePath        SaveFileName
readStruct          deleteStruct

3. Print Information Command:
printStructInfo     printStructSettingInfo
printListInfo

4. Result Command:
ResultFilePath      ResultFileName
deleteResult
save_run_time_result_Bool
resetSN
```

Help

```
Device Field Command (Calculate the electric/magnetic field in the deice.)
=====
1. Settting Command:
SettingFilePath      SettingFileName
setDefaultSetting    printDFInfo
loadDFSETTING        saveDFSETTING

2. Command in kxky domain:
kxko                 kyko                 z                 ----Parameter
runDFz_kxky          plotDFzvs kxky

3. Command in k polar domain:
ktko                 Thetakt                 z                 ----Parameter
runDFz_PolarInK      plotDFzvs kPolar


4. Write Bool:
write_EBool           write_HBool
write_TotalFieldBool
write_ForwardFieldBool write_BackwardFieldBool
write_M1M3FieldBool   write_M2M4FieldBool
write_M1FieldBool     write_M2FieldBool
write_M3FieldBool     write_M4FieldBool

5. Plot Bool:
changefigshowBool
plot_EBool            plot_HBool
plot_TotalFieldBool
plot_ForwardFieldBool plot_BackwardFieldBool
plot_M1M3FieldBool    plot_M2M4FieldBool
plot_M1FieldBool      plot_M2FieldBool
plot_M3FieldBool      plot_M4FieldBool

5. Run Time Bool:
runtime_plot
```

Calculating Workflow

Choose one method to load structure(s)



Default Setting


Print setting

```
>>> printDFInfo
Setting file path : ../SETTING/user-1
Setting file name : DFCmd.setting
kt/ko : 0.00000:0.10000:1.00000
Theta in kt/ko domain : 0.00000:10.00000:360.00000
kx/ko : -1.00000:0.10000:1.00000
ky/ko : -1.00000:0.10000:1.00000
z(nm) : -50.00000:1.00000:50.00000
Save Run Time Result : True
Run Time Plot : False

Plot Mode Bool:
True_E : True
True_H : True
Total (M1+M2+M3+M4) : True
+z (M1+M2) : False
-z (M3+M4) : False
M1 : False
M2 : False
M3 : False
M4 : False

Write Mode Bool:
True_E : True
True_H : True
Total (M1+M2+M3+M4) : True
+z (M1+M2) : True
-z (M3+M4) : True
M1 : True
M2 : True
M3 : True
M4 : True

Figure Show Bool : True
```



名稱	修改日期
log	2020/4/13 上午 09:5
materialMgr.mMgr	2020/4/13 上午 09:5
rtauCmd.setting	2020/4/12 下午 05:0
TRACmd.setting	2020/4/13 上午 09:5

All the setting would **automatically** saved into the setting file when the program **finished**. The user can set the setting at first or share the setting files with others.

Setting

```
kt/ko : 0.00000:0.10000:1.00000  
Theta in kt/ko domain : 0.00000:10.00000:360.00000
```

kt/ko and θ_{kt} setting method

```
<DFCmd> help ktco  
Set the kt/ko. (Empty for delete setting)  
[Usage] ktco [ktco] - single value, start:spacing:end, (v1,v2,v3,v4)  
  
<DFCmd> help Thetakt  
Set the polar angle in kx ky domain.  
[Usage] Thetakt [theta] - single value, start:spacing:end, (v1,v2,v3,v4)
```

```
kx/ko : -1.00000:0.10000:1.00000  
ky/ko : -1.00000:0.10000:1.00000
```

kx/ko and ky/ko setting method

```
<DFCmd> help kxko  
Set the kx/ko. (Empty for delete setting)  
[Usage] kxko [kxko] - single value, start:spacing:end, (v1,v2,v3,v4)  
  
<DFCmd> help kyko  
Set the ky/ko. (Empty for delete setting)  
[Usage] kyko [kyko] - single value, start:spacing:end, (v1,v2,v3,v4)
```

Setting

```
z(nm) : -50.00000:1.00000:50.00000
```

z setting method

```
<DFCmd> help z  
Set the simulation position z. (Empty for delete setting)  
[Usage] z [z] - single value, start:spacing:end, (v1,v2,v3,v4)
```


Run-Time Setting

```
Save Run Time Result : True
```

Whether to save the data in the memory after the calculation. If the user would like to execute plot or other data manipulation commands, the save-run-time-result bool should be “True”. However, the user should notice the memory usage when scanning a lot of parameters.

```
Save Run Time Result : True  
Run Time Plot : False
```

Whether to plot the results when calculation.

Setting

```
Plot Mode Bool:
True_E      : True
True_H      : True
Total (M1+M2+M3+M4) : True
+z (M1+M2)  : False
-z (M3+M4)  : False
M1          : False
M2          : False
M3          : False
M4          : False
```


Check whether the corresponding mode would be plot or not.

```
Write Mode Bool:
True_E      : True
True_H      : True
Total (M1+M2+M3+M4) : True
+z (M1+M2)  : True
-z (M3+M4)  : True
M1          : True
M2          : True
M3          : True
M4          : True
```

Check whether the corresponding mode would be written into a txt file or not.

Calculate Device Distribution

Bottom-emitting OLED




	MATERIAL	THICKNESS (nm)
1		
2	air	X
3	Al	120.000000
4	LiF	1.000000
5	B3PYMPM	50
6	CBP	20.000000
7	TAPC	50
8	cito	80
9	glass	X

wavelength(nm) : 480.0:10.0:600.0
 EML :
 Layerno : 5
 Position(nm) : 10.000000
 ratio : 1.000000
 QY : 1.000000
 Fluorescence : cbp_irppy2acac
 DOF : cbp_irppy2acac

Name	readfilename	readfilepath	savefilename
#Tsl	sfile-1.txt	./Example/structure/Transparent	sfile-1

Calculate Device Distribution

Transparent/ Double-emitting OLED



	MATERIAL	THICKNESS (nm)
1		
2	air	X
3	Al	10:5:20
4	LiF	1.000000
5	B3PYMPM	50
6	CBP	20.000000
7	TAPC	20
8	cito	50
9	glass	X
10		
11		
12		
13	wavelength (nm) :	450:10:650.0
14	EML :	
15	Layer no	: 5
16	Position (nm)	: 10.000000
17	ratio	: 1.000000
18	QY	: 1.000000
19	Fluorescence	: cbp_irppy2acac
20	DOF	: cbp_irppy2acac

Thin metal

1	Name	readfilename	readfilepath	savefilename
2	#Cs1	sfile-1.txt	./Example/structure/Convention	sfile-1
3				../.../Example/DFzC

Calculate Device Distribution

Bottom-emitting OLED

```
>>> changefigshowBool F
>>> save_run_time_result_Bool F
>>> ReadStructListPath ./Example/structure/Convention
>>> ReadStructListName structureList-DFzCmd.txt
>>> readStructList

Now reading structure list file ./Example/structure/Convention\structureList-DFzCmd.txt


| No./Name | filename    | savefilename | CommandID | Check | readfilepath                                               |
|----------|-------------|--------------|-----------|-------|------------------------------------------------------------|
| #Cs1     | sfile-1.txt | sfile-1      | 0.0       | X     | ./Example/structure/Convention ../../Example/DFzCmd-1/Conv |


Structure file reading...
Now reading structure file ./Example/structure/Convention\sfile-1.txt
```

Transparent/ Double-emitting OLED

```
>>> ReadStructListPath ./Example/structure/Transparent
>>> ReadStructListName structureList-DFzCmd.txt
>>> readStructList

Now reading structure list file ./Example/structure/Transparent\structureList-DFzCmd.txt


| No./Name | filename    | savefilename | CommandID | Check | readfilepath                                                  |
|----------|-------------|--------------|-----------|-------|---------------------------------------------------------------|
| #Ts1     | sfile-1.txt | sfile-1      | 0.0       | X     | ./Example/structure/Transparent ../../Example/DFzCmd-1/Transp |


Structure file reading...
Now reading structure file ./Example/structure/Transparent\sfile-1.txt
```

Calculate Device Distribution

```
>>> printStructInfo
```

```
*****
```

```
Name: #Cs1
```

```
[#] Material Thickness(nm)
```

```
-----
[1] air X
[2] Al 120.0
[3] LiF 1.0
[4] B3PYMPM 50.0
[5] CBP 20.0
[6] TAPC 50.0
[7] cito 80.0
[8] glass X
```

```
wavelength(nm) : 480.00000:10.00000:600.00000
```

```
EML Fluorescence DOF Position(nm) PLQY Ratio
```

```
-----
[5] cbp_irppy2acac cbp_irppy2acac 10.0 1.0 1.0
```

```
Device number : 1
```

```
*****
```

```
Name: #Ts1
```

```
[#] Material Thickness(nm)
```

```
-----
[1] air X
[2] Al 10.00000:5.00000:20.00000
[3] LiF 1.0
[4] B3PYMPM 50.0
[5] CBP 20.0
[6] TAPC 20.0
[7] cito 50.0
[8] glass X
```

```
wavelength(nm) : 450.00000:10.00000:650.00000
```

```
EML Fluorescence DOF Position(nm) PLQY Ratio
```

```
-----
[5] cbp_irppy2acac cbp_irppy2acac 10.0 1.0 1.0
```

```
Device number : 3
```

```
>>> #####
```

Calculate Device Distribution

```
*** Unknown syntax: #####  
>>> ktko (0,0.5,1,1.5)  
>>> Thetakt 0  
>>> z -50:1:300  
>>> runtime_plot T
```


```
>>> printDFInfo  
Setting file path : ../.. /SETTING/user-1  
Setting file name : DFCmd.setting  
kt/ko : 0.00000:0.50000:1.50000  
Theta in kt/ko domain : 0.0  
kx/ko : -1.00000:0.10000:1.00000  
kv/ko : -1.00000:0.10000:1.00000  
z(nm) : -50.00000:1.00000:300.00000  
Save Run Time Result : False  
Run Time Plot : True  
  
Plot Mode Bool:  
True_E : True  
True_H : True  
Total (M1+M2+M3+M4) : True  
+z (M1+M2) : False  
-z (M3+M4) : False  
M1 : False  
M2 : False  
M3 : False  
M4 : False  
  
Write Mode Bool:  
True_E : True  
True_H : True  
Total (M1+M2+M3+M4) : True  
+z (M1+M2) : True  
-z (M3+M4) : True  
M1 : True  
M2 : True  
M3 : True  
M4 : True  
  
Figure Show Bool : False
```

Calculate Device Distribution

[illegible]

```
A1                                10:5:20  
wavelength(nm) : 480.0:10.0:600.0
```


Data



Normal direction
TE=TM

TE
TM


MATERIAL	THICKNESS (nm)
air	X
Al	120.000000
LiF	1.000000
B3PYMPM	50
CBP	20.000000
TAPC	50
cito	80
glass	X

z

z=0

Data

The electric field of TE mode is continuous on the interface.




TE
TM

MATERIAL	THICKNESS (nm)
air	X
Al	120.000000
LiF	1.000000
B3PYMPM	50
CBP	20.000000
TAPC	50
cito	80
glass	X

z
 $z=0$


The electric field of TM mode is discontinuous on the interface.

Data



Data

The electric field of TE mode is continuous on the interface.



TE
TM

MATERIAL	THICKNESS (nm)
air	X
Al	10
LiF	1.000000
B3PYMPM	50
CBP	20.000000
TAPC	20
cito	50
glass	X

z
 $z=0$

No zero.

The electric field of TM mode is discontinuous on the interface.

Calculate Device Distribution

Exit the material manager system.

*** The material manager system would be automatically saved into the user's setting directory.

```
>>> exit
```

```
-----  
End running GOODLAB anisotropic simulator ver1.0 Sun Apr 12 22:42:34 2020  
Elapsed time : 0 day(s)/ 0 hr(s)/ 2 min(s)/ 28.69119143486023 sec(s)  
-----
```

